管理者コンソール > ユーザー管理 >

# **Ping Identity SCIM Integration**

ヘルプセンターで表示: https://bitwarden.com/help/ping-identity-scim-integration/

### **Ping Identity SCIM Integration**

System for cross-domain identity management (SCIM) can be used to automatically provision and de-provision members and groups in your Bitwarden organization.

### (i) Note

```
SCIMインテグレーションは、エンタープライズ組甔で利用可能です。SCIM互換のIDプロバイダーを使用していないチーム組甔、
または顧客は、プロビジョニングの代替手段としてディレクトリコネクタの使用を検討することがあります。
```

This article will help you configure a SCIM integration with Ping Identity. Configuration involves working simultaneously with the Bitwarden web vault and Ping Identity Administrator dashboard. As you proceed, we recommend having both readily available and completing steps in the order they are documented.

### **Enable SCIM**

```
    Note
    あなたは自己ホスト型のBitwardenを使用していますか?それなら、
進む前にサーバーでSCIMを有効にするためのこれらの手順を完了してください。
```

To start your SCIM integration, open the Admin Console and navigate to **Settings** → **SCIM provisioning**:

<b>U bit</b> Warden	SCIM provisioning	
∅ My Organization ☐ Collections	<ul> <li>Automatically provision users and groups with your preferred identity provider via SCIM provisioning</li> <li>Enable SCIM</li> </ul>	
은 Members 뿅 Groups	Set up your preferred identity provider by configuring the URL and SCIM API Key SCIM URL	
₩ Reporting	SCIM API key	© 0 0
_ <b>U</b>	This API key has access to manage users within your organization. It should be kept secret.	
Organization info Policies	Save	
Two-step login Import data		
Export vault Domain verification		
Single sign-on		
Device approvals		
	SCIM プロビジョニング	

Select the Enable SCIM checkbox and take note of your SCIM URL and SCIM API Key. You will need to use both values in a later step.

### **Create a SCIM app**


1. Navigate to provisioning  $\oplus$  **New Connection**.

• Getting Started	Provisioning 🕕			
Overview	Administrators can manage their provisioning connections. A connection contains configuration that tells PingOne how to connect to an external resource for the purpose of provisioning user to that resource. Learn More			
ル Monitoring 🗸	Rules Connections			
🐣 Directory 🔹	Q			
Applications -				
	0 Connections by Name -			
<ul> <li>Authentication •</li> </ul>				
Threat Protection +				
💉 Integrations 🔶				
External IdPs				
Provisioning				

Ping Identity new Connection

2. In the Create a New Connection window, choose the Select option for Identity Store.

3. In the Identity Store, enter SCIM into the search box and select SCIM Outbound. Once this step is complete, select Next.



SCIM Connection

4. Input a Name and Description for the SCIM connection.

- 5. Next, you will be required to input the SCIM BASE URL. Copy the SCIM URL value located on the Enable SCIM page in the Bitwarden Admin Console and paste it into this field.
- 6. Using the Authentication Method dropdown menu, select OAuth 2 Bearer Token. A field will appear named Oauth Access Token, paste the SCIM API key value from the Bitwarden Admin Console into this field.

 $\times$ 





Specify the authentication configuration for the connection.

### **Configure Authentication**

SCIM BASE URL *		Users Resource
https://vault.bitwarden.pw/scim/v2/	/Users	
SCIM version		Groups Resource
2.0	•	/Groups
Authentication Method		
OAuth 2 Bearer Token	•	
Oauth Access Token *		
•••••	Ø	
Auth Tura Haadar		
Auth Type Header		
Bearer	•	

Previous

Cancel

Test Connection

Next

Ping Identity SCIM connection test

7. Once setup is complete, you may select Test Connection. If successful, select Next.


8. On the Configure Preferences page, select desired preferences and actions.

#### (i) Note

Setting the Remove Action setting to **Disable** will result in Bitwarden users being moved to **Revoked** status rather if the user fails to meet the filter criteria set on Ping Identity. Restoring the criteria will return the user to their **previous** state.

If the Remove Action is set to Delete, the same action will deprovision the user.

9. Select Save once complete. Select the newly created Connection and enable the Connection using the toggle.




Enable Ping Identity Connection

### **Create a Rule**

Before syncing user groups and directories, a Rule is required to sync the user groups to Bitwarden SCIM.

- 1. Return to the Provisioning Screen.
- 2. Select the **Rules** tab and then  $\oplus$  **New Rule**.
- 3. Enter an app specific name for the Rule and select Create Rule.
- 4. Edit the new Rule in the Configuration tab. Select Bitwarden SCIM connection and then Save.



Ping Identity Rule


5. Select the Configuration tab and add a 2 User Filter. For more information, see the Ping Identity documentation. Select Save once complete.

(Add +
Value @my-company.com
Value US

Ping Identity User Filter

6. Enable the Rule using the toggle.





2. Choose the group or groups to provision and select **Save**. Once saved, the directory will trigger a sync.

### Appendix

#### **Required attributes**

Both the Bitwarden and Ping Identity **SCIM Provisioner with SAML (SCIM v2 Enterprise)** applications use standard SCIM v2 attribute names. Bitwarden will use the following attributes:

### User attributes

- active
- emails<sup>a</sup> or userName
- displayName
- externalId

<sup>a</sup> - Because SCIM allows users to have multiple email addresses expressed as an array of objects, Bitwarden will use the value of the object which contains "primary": true.

### **Group attributes**

For each group, Bitwarden will use the following attributes:

- displayName (required)
- members<sup>a</sup>
- externalId

<sup>a</sup> - members is an array of objects, each object representing a user in that group.